

N O T I C E

THIS DOCUMENT HAS BEEN REPRODUCED FROM
MICROFICHE. ALTHOUGH IT IS RECOGNIZED THAT
CERTAIN PORTIONS ARE ILLEGIBLE, IT IS BEING RELEASED
IN THE INTEREST OF MAKING AVAILABLE AS MUCH
INFORMATION AS POSSIBLE

"Made available under NASA sponsorship
in the interest of early and wide dis-
semination of Earth Resources Survey
Program information and without liability
for any use made thereof."

8.0 - 10217

NASA CR-

160621

JSC-13055

**"AS-BUILT" DESIGN SPECIFICATION
FOR
BOUNDARY DETECTION AND REGISTRATION
PROGRAM (BDARP1)**

Job Order 71-695

(TIRF 76-0046)

**(E80-10217) AS-BUILT DESIGN SPECIFICATION
FOR BOUNDARY DETECTION AND REGISTRATION
PROGRAM (BDARP1) (Lockheed Electronics Co.)
116 p HC A06/MF A01**

N80-29794

CSCL 05B

Unclass

G3/43 00217

**Prepared By
Lockheed Electronics Company, Inc.
Systems and Services Division
Houston, Texas**

Contract NAS 9-15200

**For
EARTH OBSERVATIONS DIVISION
SCIENCE AND APPLICATIONS DIRECTORATE**



**National Aeronautics and Space Administration
LYNDON B. JOHNSON SPACE CENTER**

Houston, Texas

August 1977

LEC-11074

JSC-13055

"AS-BUILT" DESIGN SPECIFICATION
FOR
BOUNDARY DETECTION AND REGISTRATION
PROGRAM (BDARPl)

Job Order 71-695

(TIRF 76-0046)

Prepared By

D. P. McKay

F. Collen

APPROVED BY


Philip L. Krumm, Supervisor
Applications Software Section

Prepared By

Lockheed Electronics Company, Inc.

For

Earth Observations Division
Science and Applications Directorate

NATIONAL AERONAUTICS AND SPACE ADMINISTRATION
LYNDON B. JOHNSON SPACE CENTER
HOUSTON, TEXAS

August 1977

LEC-11074

CONTENTS

Section	Page
1. SCOPE	1-1
1.1 <u>GENERAL</u>	1-1
2. APPLICABLE DOCUMENTS	2-1
3. SYSTEM DESCRIPTION	3-1
3.1 <u>HARDWARE DESCRIPTION</u>	3-2
3.2 <u>SOFTWARE DESCRIPTION</u>	3-2
3.2.1 SOFTWARE COMPONENT NO. 1 (DRVF)	3-4
3.2.1.1 <u>Linkage</u>	3-4
3.2.1.2 <u>Interface</u>	3-4
3.2.1.3 <u>Input</u>	3-4
3.2.1.4 <u>Output</u>	3-4
3.2.1.5 <u>Storage Requirements</u>	3-5
3.2.1.6 <u>Description</u>	3-5
3.2.1.7 <u>Flowchart</u>	3-6
3.2.1.8 <u>Listing</u>	3-7
3.2.2 SOFTWARE COMPONENT NO. 2 (REAHD)	3-8
3.2.2.1 <u>Linkage</u>	3-8
3.2.2.2 <u>Interface</u>	3-8
3.2.2.3 <u>Input</u>	3-8
3.2.2.4 <u>Output</u>	3-8
3.2.2.5 <u>Storage Requirements</u>	3-8
3.2.2.6 <u>Description</u>	3-9
3.2.2.7 <u>Flowchart</u>	3-10

Section	Page
3.2.2.8 <u>Listing</u>	3-11
3.2.3 SOFTWARE COMPONENT NO. 3 (REAHF)	3-13
3.2.3.1 <u>Linkage</u>	3-13
3.2.3.2 <u>Interface</u>	3-13
3.2.3.3 <u>Input</u>	3-13
3.2.3.4 <u>Output</u>	3-13
3.2.3.5 <u>Storage Requirements</u>	3-13
3.2.3.6 <u>Description</u>	3-13
3.2.3.7 <u>Flowchart</u>	3-15
3.2.3.8 <u>Listing</u>	3-16
3.2.4 SOFTWARE COMPONENT NO. 4 (INITN)	3-19
3.2.4.1 <u>Linkage</u>	3-19
3.2.4.2 <u>Interface</u>	3-19
3.2.4.3 <u>Input</u>	3-19
3.2.4.4 <u>Output</u>	3-19
3.2.4.5 <u>Storage Requirements</u>	3-19
3.2.4.6 <u>Description</u>	3-19
3.2.4.7 <u>Flowchart</u>	3-20
3.2.4.8 <u>Listing</u>	3-21
3.2.5 SOFTWARE COMPONENT NO. 5 (CON79)	3-23
3.2.5.1 <u>Linkage</u>	3-23
3.2.5.2 <u>Interface</u>	3-23
3.2.5.3 <u>Input</u>	3-23
3.2.5.4 <u>Output</u>	3-23
3.2.5.5 <u>Storage Requirements</u>	3-23

Section	Page
3.2.5.6 <u>Description</u>	3-23
3.2.5.7 <u>Flowchart</u>	3-24
3.2.5.8 <u>Listing</u>	3-25
3.2.6 SOFTWARE COMPONENT NO. 6 (RDLIN)	3-28
3.2.6.1 <u>Linkage</u>	3-28
3.2.6.2 <u>Interface</u>	3-28
3.2.6.3 <u>Input</u>	3-28
3.2.6.4 <u>Output</u>	3-28
3.2.6.5 <u>Storage Requirements</u>	3-28
3.2.6.6 <u>Description</u>	3-28
3.2.6.7 <u>Flowchart</u>	3-29
3.2.6.8 <u>Listing</u>	3-30
3.2.7 SOFTWARE COMPONENT NO. 7 (ISET)	3-34
3.2.7.1 <u>Linkage</u>	3-34
3.2.7.2 <u>Interface</u>	3-34
3.2.7.3 <u>Input</u>	3-34
3.2.7.4 <u>Output</u>	3-34
3.2.7.5 <u>Storage Requirements</u>	3-34
3.2.7.6 <u>Description</u>	3-34
3.2.7.7 <u>Flowchart</u>	3-35
3.2.7.8 <u>Listing</u>	3-36
3.2.8 SOFTWARE COMPONENT NO. 8 (FRAME)	3-37
3.2.8.1 <u>Linkage</u>	3-37
3.2.8.2 <u>Interface</u>	3-37
3.2.8.3 <u>Input</u>	3-37

Section	Page
3.2.8.4 <u>Output</u>	3-37
3.2.8.5 <u>Storage Requirements</u>	3-37
3.2.8.6 <u>Description</u>	3-37
3.2.8.7 <u>Flowchart</u>	3-38
3.2.8.8 <u>Listing</u>	3-39
3.2.9 SOFTWARE COMPONENT NO. 9 (LINIT)	3-40
3.2.9.1 <u>Linkage</u>	3-40
3.2.9.2 <u>Interface</u>	3-40
3.2.9.3 <u>Input</u>	3-40
3.2.9.4 <u>Output</u>	3-40
3.2.9.5 <u>Storage Requirements</u>	3-40
3.2.9.6 <u>Description</u>	3-40
3.2.9.7 <u>Flowchart</u>	3-42
3.2.9.8 <u>Listing</u>	3-43
3.2.10 SOFTWARE COMPONENT NO. 10 (BDT3)	3-44
3.2.10.1 <u>Linkage</u>	3-44
3.2.10.2 <u>Interface</u>	3-44
3.2.10.3 <u>Input</u>	3-44
3.2.10.4 <u>Output</u>	3-44
3.2.10.5 <u>Storage Requirements</u>	3-44
3.2.10.6 <u>Description</u>	3-44
3.2.10.7 <u>Flowchart</u>	3-46
3.2.10.8 <u>Listing</u>	3-48
3.2.11 SOFTWARE COMPONENT NO. 11 (READAT)	3-55
3.2.11.1 <u>Linkage</u>	3-55
3.2.11.2 <u>Interface</u>	3-55

Section	Page
3.2.11.3 <u>Input</u>	3-55
3.2.11.4 <u>Output</u>	3-55
3.2.11.5 <u>Storage Requirements</u>	3-55
3.2.11.6 <u>Description</u>	3-55
3.2.11.7 <u>Flowchart</u>	3-57
3.2.11.8 <u>Listing</u>	3-58
3.2.12 SOFTWARE COMPONENT NO. 12 (IGET)	3-59
3.2.12.1 <u>Linkage</u>	3-59
3.2.12.2 <u>Interface</u>	3-59
3.2.12.3 <u>Input</u>	3-59
3.2.12.4 <u>Output</u>	3-59
3.2.12.5 <u>Storage Requirements</u>	3-59
3.2.12.6 <u>Description</u>	3-59
3.2.12.7 <u>Flowchart</u>	3-60
3.2.12.8 <u>Listing</u>	3-61
3.2.13 SOFTWARE COMPONENT NO. 13 (FILL)	3-62
3.2.13.1 <u>Linkage</u>	3-62
3.2.13.2 <u>Interface</u>	3-62
3.2.13.3 <u>Input</u>	3-62
3.2.13.4 <u>Output</u>	3-62
3.2.13.5 <u>Storage Requirements</u>	3-62
3.2.13.6 <u>Description</u>	3-62
3.2.13.7 <u>Flowchart</u>	3-63
3.2.13.8 <u>Listing</u>	3-65
3.2.14 SOFTWARE COMPONENT NO. 14 (FINDAR) . . .	3-67

Section	Page
3.2.14.1 <u>Linkage</u>	3-67
3.2.14.2 <u>Interface</u>	3-67
3.2.14.3 <u>Input</u>	3-67
3.2.14.4 <u>Output</u>	3-67
3.2.14.5 <u>Storage Requirements</u>	3-67
3.2.14.6 <u>Description</u>	3-67
3.2.14.7 <u>Flowchart</u>	3-68
3.2.14.8 <u>Listing</u>	3-69
3.2.15 SOFTWARE COMPONENT NO. 15 (CONNECT) . . .	3-72
3.2.15.1 <u>Linkage</u>	3-72
3.2.15.2 <u>Interface</u>	3-72
3.2.15.3 <u>Input</u>	3-72
3.2.15.4 <u>Output</u>	3-72
3.2.15.5 <u>Storage Requirements</u>	3-72
3.2.15.6 <u>Description</u>	3-72
3.2.15.7 <u>Flowchart</u>	3-73
3.2.15.8 <u>Listing</u>	3-74
3.2.16 SOFTWARE COMPONENT NO. 16 (CONALL) . . .	3-76
3.2.16.1 <u>Linkage</u>	3-76
3.2.16.2 <u>Interface</u>	3-76
3.2.16.3 <u>Input</u>	3-76
3.2.16.4 <u>Output</u>	3-76
3.2.16.5 <u>Storage Requirements</u>	3-76
3.2.16.6 <u>Description</u>	3-76
3.2.16.7 <u>Flowchart</u>	3-77

Section	Page
3.2.16.8 <u>Listing</u>	3-79
3.2.17 SOFTWARE COMPONENT NO. 17 (JOIN)	3-81
3.2.17.1 <u>Linkage</u>	3-81
3.2.17.2 <u>Interface</u>	3-81
3.2.17.3 <u>Input</u>	3-81
3.2.17.4 <u>Output</u>	3-81
3.2.17.5 <u>Storage Requirements</u>	3-81
3.2.17.6 <u>Description</u>	3-81
3.2.17.7 <u>Flowchart</u>	3-82
3.2.17.8 <u>Listing</u>	3-83
3.2.18 SOFTWARE COMPONENT NO. 18 (CLSTST) . . .	3-85
3.2.18.1 <u>Linkage</u>	3-85
3.2.18.2 <u>Interface</u>	3-85
3.2.18.3 <u>Input</u>	3-85
3.2.18.4 <u>Output</u>	3-85
3.2.18.5 <u>Storage Requirements</u>	3-85
3.2.18.6 <u>Description</u>	3-85
3.2.18.7 <u>Flowchart</u>	3-86
3.2.18.8 <u>Listing</u>	3-87
3.2.19 SOFTWARE COMPONENT NO. 19 (AREAL)	3-88
3.2.19.1 <u>Linkage</u>	3-88
3.2.19.2 <u>Interface</u>	3-88
3.2.19.3 <u>Input</u>	3-88
3.2.19.4 <u>Output</u>	3-88
3.2.19.5 <u>Storage Requirements</u>	3-88

Section	Page
3.2.19.6 <u>Description</u>	3-88
3.2.19.7 <u>Flowchart</u>	3-89
3.2.19.8 <u>Listing</u>	3-90
3.2.20 SOFTWARE COMPONENT NO. 20 (ENDTST) . . .	3-91
3.2.20.1 <u>Linkage</u>	3-91
3.2.20.2 <u>Interface</u>	3-91
3.2.20.3 <u>Input</u>	3-91
3.2.20.4 <u>Output</u>	3-91
3.2.20.5 <u>Storage Requirements</u>	3-91
3.2.20.6 <u>Description</u>	3-91
3.2.20.7 <u>Flowchart</u>	3-92
3.2.20.8 <u>Listing</u>	3-93
4. OPERATION	4-1
4.1 <u>USER DOCUMENTATION</u>	4-1
4.2 <u>OPERATOR DOCUMENTATION</u>	4-1

Appendix

A. BDARPl COMMON TABLE	A-2
----------------------------------	-----

FIGURES

Figure	Page
1. Functional Diagram of Phase I Implementation of the Software System	4-2
2. Bendix System 100 Core Utilization Map	4-3
3. User's Procedure	4-4
4. The Functional Block Diagram of BDARPl	4-6

APPENDIX

1. BDARPl Common Table	A-2
----------------------------------	-----

1. SCOPE

This document describes the detailed design characteristics of the Boundary Detection and Registration Program (BDARPl), as built for the Bendix 100 Interactive Drafting System. The BDARPl is an unsophisticated version of the final software system, yet it provides the user with the basic capabilities of obtaining classified data boundary plots, editing, and registration of the final boundary plot to a user-selected base.

2. APPLICABLE DOCUMENTS

The following documents form a part of this specification to the extent specified herein:

- Technical Memorandum Software Specifications for Automated Thematic Plotting of Classified Digital Data, LEC-8289
- Technical Memorandum Project Development Plan for the Bendix Interactive Drafting System Modification, LEC-8968
- Design Specification for Automated Thematic Plotting of Classified Digital Data, LEC-9506
- Technical Memorandum Acceptance Test Plan for Boundary Detection and Registration Program (BDARPl), LEC-10672
- TIRF 76-0046

3. SYSTEM DESCRIPTION

The Boundary Detection and Registration Program (BDARPl) was designed and implemented as an addition to the basic Bendix 100 Drafting Program. The BDARPl consists of three overlays:

USER08 - the classified tape initialization module

T2 - the tape read and data storage routine

T3 - the boundary detection and registration algorithm

To begin processing, USER08 accepts the user's options and reads the header record from a 7-track, 800 BPI, even parity universal formatted classified tape directly or indirectly obtained from the GE Interactive Multispectral Image Analyst System (Image 100), the Earth Resources Interactive Processing System (ERIPS) or the UNIVAC 1100 Software.

USER08 then calls overlay T2, which reads the required number of data records from the magnetic tape. The data are processed, packed and written on a temporary disk file, TDATA. Corner reference ticks are placed on the drawing file.

Overlay T2 calls the third and last overlay - T3. Overlay T3 reads the data stored in TDATA, one line at a time, and performs the boundary detection and registration algorithm. The resultant boundary information is written into a standard format drawing file, and control is then returned to the basic Bendix 100 Drafting Program. Editing and write tape functions are now available to prepare the boundary data for plotting.

BDARPl is designed to process one class at a time. For the case of multiple classes, BDARPl has to run as many times as the number of classes. Each execution of BDARPl under the Drafting Program is initialized by selecting USER OPTION:8 on the menu.

When processing is completed, BDARPl informs the user by sounding the tone on the display device (Tektronix) and illuminating the red indicator light on the digitizer cursor.

Note that the editing and tape write functions are currently available under Bendix System 100 and can be used as long as the drawing file format used to store the boundary strings by the boundary detection routine is identical to the one employed by the Bendix System 100 software. Since no additional software is required for the editing and write tape routines, these two are not included in the software description. However, as a result, it imposes a restriction on the file format to be used to store the boundary strings.

3.1 HARDWARE DESCRIPTION

Bendix System 100 configuration.

3.2 SOFTWARE DESCRIPTION

In this section each of the three overlays which form an integral part of BDARPl is further broken down into subroutines. Brief functional descriptions of each subroutine as well as inter-subroutine relationships are discussed.

Overlay USER08 is the initialization module for BDARPl, and consists of the following routines:

DRVF - the driver routine for this overlay

INPBD - the subroutine which interacts with the operator to accomplish input of the control parameters

REAHD - subroutine which reads the header record on the classified input tape

INITN - subroutine which error checks header record data and positions the tape for reading the image data

CON79 - subroutine which converts unformatted input data to byte data

The second overlay, T2, which performs input of classified data, consists of the following routines:

RDLIN - reads the classified data tape and packs the data into a temporary disk file, TDATA

ISSET - sets the appropriate bits in 16 bit words to indicate which pixels belong to the class being examined. These words are the packed data which RDLIN packs into TDATA

CON79 - same as CON79 in overlay USER08

FRAME - subroutine which inserts corner ticks in the drawing file

LINIT - subroutine which performs 8-parameter transformation to the data and sends it to the System 100 drawing file

The third and final overlay in BDARPl is designated T3. This overlay is the boundary detection algorithm, which examines the packed data in TDATA, creates boundary strings to represent the boundaries of the specified data class, and writes these boundary strings into a drawing file formatted for the Bendix system. The routines which comprise overlay T3 are:

BDT3 - This is the main routine for T3 and the principal routine for the boundary detection algorithm.

READAT - This subroutine reads bit images of line data from the temporary disk file, TDATA.

IGET - This subroutine unpacks the bit data read into READAT for the boundary detection algorithm.

FILL - This routine redefines appropriate pixels as "classified" to facilitate connectivity as defined by the user input parameter Epsilen.

FINDAR - Subroutine which finds the appropriate boundary string to which a boundary line segment belongs.

CONECT; CONALL; JOIN - Subroutines which link appropriate boundary strings.

CLSTST - Subroutine which periodically checks the status of boundary strings for completeness, and processes the complete ones.

AREAL - Subroutine which computes the area in pixel units of each classified group.

LINIT - Subroutine which performs 8-parameter transformation to the data and sends it to the System 100 drawing file.

ENDTST - Subroutine which handles segmentation of large plot string arrays.

3.2.1 SOFTWARE COMPONENT NO. 1 (DRVF)

3.2.1.1 Linkage

Subroutine DRVF calls user subroutines INPBD and INITN, and calls the system subroutine FRNOV.

3.2.1.2 Interface

DRVF is linked with the common block ICONS (see Appendix A) which houses all the basic control parameters for BDARPl.

3.2.1.3 Input

None

3.2.1.4 Output

An error message is output including an error code whenever the system subroutine FRNOV fails.

3.2.1.5 Storage Requirements

Subroutine DRVF requires 184 words in core.

3.2.1.6 Description

DRVF is the driver for the initial overlay USER08, and calls overlay T2 into core after USER08 has been executed.

3.2.1.7 Flowchart

3.2.1.8 Listing

(DRVF)

ORIGINAL PAGE IS
OF POOR QUALITY

START

INPBD

Obtain file no.,
Tape parity, and
First line no.

INITN

Read Header
Record and
Position tape to
First line no.

INPBD

Obtain remaining
Input parameters
from operator

Store input
from INPBD into
common block
/ICONS/

FRNOV

(System sub-
routine) bring
overlay T2 into
core, and
Execute T2

END

```

COMMON /ICONS/ IO(14), OPTNS(16), ISET
DIMENSION IG0(5), IDENT(20), IALPH(5)
IALPH(1)="T2"
IALPH(2)="/1"
CALL INPBD(1)
CALL INITN
CALL INPBD(2)
IALPH(3)=0
IER=0
CALL FRNOU(IALPH,IER)
PAUSE DIDNT USE FRNOU SUCCESSFULLY
WRITE(10,1001) IER
1001 FORMAT(10X,"IER =",I4)
C PAUSE OVERLAY ERROR-NO RETURN TO SYSTEM 101
END

READY

```

3.2.2 SOFTWARE COMPONENT NO. 2 (INPBD)

3.2.2.1 Linkage

Subroutine INPBD is called by DRVF.

3.2.2.2 Interface

The basic common block ICONS (see Appendix A) which houses all the necessary control parameters is created by subroutine INPBD.

3.2.2.3 Input

All the basic information which BDARPl needs for execution is requested and received by INPBD via the teletype or display screen and keyboard. The operator is queried for the following:

1. Tape file no.
2. Parity (0 or 1)
3. First line no.
4. Last line no.
5. First pixel no.
6. Last pixel no.
7. Channel no.
8. Class value
9. Epsilon value
10. Kappa value
11. Eight coefficients for registration (optional)

3.2.2.4 Output

The above control parameter queries are displayed on the screen.

3.2.2.5 Storage Requirements

Subroutine INPBD requires 584 words in core.


3.2.2.6 Description

Subroutine INPBD interacts with the operator to bring in the basic control parameters for BDARPl execution, and defines them as components of the vector OPTNS (see Appendix A) which is part of the common block ICONS.

3.2.2.7 Flowchart

3.2.2.8 Listing

(INPBD)



LIST LINES - 33

READY

```
SUBROUTINE INPBD (LL)
COMMON /ICONS/ ID(14),OPTNS(16),ISET
IF(LL NE 1) GO TO 101

WRITE(10,1)
1  FORMAT(10X,"*****      BOUNDARY DETECTION PROGRAM      *****",
/28X,"VERSION 1",//////)
WRITE(10,2)
2  FORMAT(20X,"ENTER:",/23X,"1. TAPE FILE NO.  =")
READ (11) OPTNS(2)
WRITE(10,21)
21 FORMAT(23X,"2. PARITY(0 OR 1) =")
READ (11) OPTNS(3)
WRITE(10,22)
22 FORMAT(23X,"3. FIRST LINE NO. =")
READ (11) OPTNS(1)
RETURN
101 CONTINUE
WRITE(10,3)
3  FORMAT(23X,"4. LAST LINE NO.  =")
READ (11) OPTNS(2)
WRITE(10,4)
4  FORMAT(23X,"5. FIRST PIXEL NO. =")
READ (11) OPTNS(3)
WRITE(10,5)
5  FORMAT(23X,"6. LAST PIXEL NO. =")
READ (11) OPTNS(4)
WRITE(10,6)
6  FORMAT(23X,"7. CHANNEL NO.    =")
READ (11) OPTNS(5)
WRITE(10,7)
7  FORMAT(23X,"8. CLASS VALUE    =")
READ (11) OPTNS(6)
```

LIST LINES - 33

```

      WRITE(10,8)
5  FORMAT(23X,"9. EPSILON VALUE  =")
   READ (11) OPTNS(7)
   WRITE(10,9)
6  FORMAT(22X,"10 KAPPA VALUE  =")
   READ(11) OPTNS(8)
   WRITE(10,10)
10  FORMAT(10X,"ENTER EIGHT COEFFICIENTS FOR REGISTRATION",
     10X,"OR",10X,"ENTER 999 AS THE FIRST COEFFICIENT")
   DO 100 I=1,8
   WRITE(10,11) I
11  FORMAT(15X,"COEFFICIENT ",I1," =")
      J=I+8
      READ (11) OPTNS(J)
      NOP=OPTNS(J)
      IF NOP=999) 100,120,100
100  CONTINUE
      GO TO 130
120  DO 200 N=10,16
200  OPTNS(N) = 0.0
      OPTNS(9) = 1.0
      OPTNS(15) = 1.0
130  CALL FCNOT("!")
      RETURN
      END

```

READY

3.2.3 SOFTWARE COMPONENT NO. 3 (REAHF)

3.2.3.1 Linkage

Subroutine REAHF is called in overlay USER08 by subroutine INITN, and calls subroutines CON79 and RDTAPE (a system subroutine which affects magnetic tape reading).

3.2.3.2 Interface

The control information from the header record, and the information needed to read the header record, is transmitted through the common block ICONS.

3.2.3.3 Input

The subroutine reads the header record on the data tape.

3.2.3.4 Output

Error messages may be displayed to the operator if subroutine REAHF encounters ambiguities in the header information.

3.2.3.5 Storage Requirements

Subroutine REAHF requires 650 words in core.

3.2.3.6 Description


The main purpose of subroutine REAHF is to read the header record from the designated file on the data tape. A conversion using CON79 is required to obtain descriptive values. These elements are tested and, if valid, are stored in the vector ID in the common block ICONS. If adequate information to process the data is not available, a message to that effect alerts the operator and the run is terminated. Under certain conditions, however, when only one or two parameters are in error, the subroutine will supply "standard" values for the one or two in error, and execution

of BDARPl will be attempted. An appropriate warning will be communicated to the operator under this condition.

3.2.3.7 Flowchart

3.2.3.8 Listing

(REAH)



3-15

17

READY

```
SUBROUTINE REAMD (NOHD)
COMMON /ICONS/ ID(14), OPTNS(16)/ IFLAG
DIMENSION IAK(4000), INK(2), IB(3)
DATA IHD /0/
DATA LIST /5,7,11,11,2,3,1,4,4,8,12,12,9,10,10,6,6/
DATA IBYTE /90,91,92,93,102,103,104,105,106,107,108,109,1778,
1785,1786,1787,1788/
IF (IHD) 160, 20, 160
20  NIT = 0
   N = 4000
   IPAR = OPTNS(3)
   CALL ROTAPE(NIT, IA, N, IPAR, KSHR, JCON)
   INK(1) = IAK(1)
   INK(2) = IAK(2)
   CALL CON79 (IN, IB)
   IF (IB(1)) 70, 30, 70
30  IF (IB(2) - 1) 70, 35, 70
   35  WRITE (10,535) IB(2)
535  FORMAT (1X, " SINCE FIRST WORD = ", I3, ", THIS RECORD APPEARS TO
      BE DATA INSTEAD HEADER. WILL TRY TO USE STANDARD VALUES.")
C*** NOHD = 1 FOR I-100, 2 FOR LARSYS AND 3 FOR 1100.
   IF (NOHD - 2) 40, 50, 60
40  ID(1) = 1
   ID(2) = 0
   ID(3) = 0
   ID(4) = 70
   ID(5) = 3
   ID(6) = 500
   ID(7) = 8
   ID(8) = 0
   ID(9) = 1
   ID(10) = 3
   ID(11) = 1
```

ORIGINAL PAGE IS
OF POOR QUALITY

READY

```
      ID (12) = 1
      GO TO 160
50    GO TO 40
C***  USE I-100 UNTIL VALUES FOR LARSYS AVAILABLE
60    GO TO 40
C ***  INSERT UNIVAC CONSTANTS WHEN AVAILABLE
70    I = 57
      K = 87
      L = 1
80    I = I + 2
      IF (I - 75) 90, 85, 90
85    I = 1185
      K = 1776
90    IN(1) = IA(I)
      IN(2) = IA(I + 1)
      CALL CON79 (IN, IB)
      IMD = IA(I + 1)
C      WRITE (10,930) IN,IB, IA(I), IMD, I, K, L
C ***  PUT VALUES FROM TAPE INTO BYTE
      DO 100 N = 1,3
      K = K + 1
      IF (K - IBYTE(L)) 100, 95, 105
95    IBYTE(L) = IB(N)
      L = L + 1
100   CONTINUE
      IF (I - 1191) 80, 110, 110
105   WRITE (10,605) K, IBYTE(L)
605   FORMAT (1X," HOW CAN K = ", I3," WHICH IS LARGER THAN", I4)
C ***  TEST FOR TWO-BYTE WORDS AND STORE IN ID
110   L = 1
120   IF (L - 16) 130, 130, 160
130   N = LIST(L)
      K = L + 1
```

```

      IF (LIST(L) - LIST(K)) 140, 150, 140
140   ID(N) = IBYTE(L)
      L = L + 1
      GO TO 120
150   IWD = IBYTE(L) * 400K + IBYTE(K)
      ID(N) = IWD
      L = L + 2
      GO TO 120
160   IHD = 1
C     WRITE (10,650) ID
C 650  FORMAT (1X, 10X, "HEADER VALUES FROM TAPE."//2(7I6//))
C *** IHD FLAG SHOWS HEADER RECORD HAS BEEN READ.
      RETURN
      END

```

READY

3.2.4 SOFTWARE COMPONENT NO. 4 (INITN)

3.2.4.1 Linkage

Subroutine INITN is called by the driver subroutine DRVF in overlay USER08, and in turn calls user subroutines REAHD and CON79 and system subroutines RDTAPE and SPACE.

3.2.4.2 Interface

The common block ICONS transmits control information to INITN.

3.2.4.3 Input

See 3.2.4.2.

3.2.4.4 Output

None

3.2.4.5 Storage Requirements

Subroutine INITN requires 396 words in core.


3.2.4.6 Description

Subroutine INITN begins by positioning the input tape to the requested file and reading the header record via subroutine REAHD. Additional error checks are performed on the header data, then the input tape is positioned to the record containing the first data line requested by the user.

3.2.4.7 Flowchart

3.2.4.8 Listing

(INITN)



READY

```
SUBROUTINE INITN
COMMON /ICONS/ ID(14), OPTNS(16), IFLG1
DIMENSION IA(4080), INK(2), IB(3)
ISYS=1
IFLG1=0
NIT = 0
IFLSK = OPTNS(2)
IFLG1 = 1
N = IFLSK - 1
IF (N) 50,50,40
40 N = N - 1
CALL SPACE (NIT, IFLG1, NIT, ISTAT)
IF (N) 50,50,40
50 CALL REAHQ (ISYS)
IANS = 1
C*** HEADER DATA TEST BY MINTER.
C*** ONE CHANNEL MUST NOT BE LARGER THAN ONE RECORD.
IF (ID(3) - 1) 80,80,75
75 WRITE (10,575) ID(3)
C*** OR SUM ERRORS USING IERR = IERR + 2
575 FORMAT (1X," FLAG3 = ", I4,". INDICATES CHANNEL LARGER THAN "
"RECORD.")
ID(3) = 1
C*** START OF VIDEO DATA SHOULD BE GREATER THAN ZERO.
80 IF (ID(1)) 85,85,90
85 ID(1) = 1
C*** NUMBER OF DATA SETS PER RECORD IS GREATER THAN ZERO.
90 IF (ID(9)) 95,95,100
95 ID(9) = 1
C*** EXPECT 8 BITS FROM ORIGINAL DATA IN BYTES.
100 IF (ID(7) - 8) 105,110,105
C*** AGAIN FOR ERROR SUM, IERR = IERR + 4
105 WRITE (10,600) ID(7)
```

```

600  FORMAT (1X," NO OF BITS = ", I5)
      IK(7) = 8
C*** POSITION TAPE TO START OF REQUESTED DATA.
110  ITEM = OPTNS(1)
C    WRITE (10,610) NIT, ISTAT
C 610  FORMAT (1X," READ DATA RECORD NEXT.  PARITY = ", I5, "  STAT=", I6)
      ISTAT = 8192
      N = 4080
120  CALL ROTAPE (NIT, IA, N, NIT, KSHRT, ISTAT)
      IN(1) = IA(47)
      IN(2) = IA(48)
      CALL CON79 (IN, IB)
      IF (IB(3) - ITEM) 120,140,130
130  WRITE (10,630) IFLSK, IB(3)
630  FORMAT (1X," ON FILE ", I4," FIRST LINE IS", I5)
140  MNUS = -1
      CALL SPACE (NIT, NIT, MNUS, ISTAT)

      RETURN
      END

```

READY

3.2.5 SOFTWARE COMPONENT NO. 5 (CON79)

3.2.5.1 Linkage

Subroutine CON79 is called by subroutines INITN and REAHD in overlay USER08 and by RDLIN in overlay T2.

3.2.5.2 Interface

Interface is accomplished by one input argument and one output argument.

3.2.5.3 Input

The input argument IA is a two-word array read from 7-track tape.

3.2.5.4 Output

The argument IB is a 3-word output array, one byte/word, right justified.

3.2.5.5 Storage Requirements

Subroutine CON79 requires 64 words in core.


3.2.5.6 Description

Subroutine CON79 is designed to convert 7-track unformatted input data to formatted information in the form it originally appeared in a 9-track tape format. It is specifically designed to restore the data to its form as it appears on a Universally formatted classified tape.

3.2.5.7 Flowchart

3.2.5.8 Listing

(CON79)



~~3-24~~
26

LIST LINES - 33

READY

TITLE CON79
PROGRAM ID-SUBROUTINE CON79
PROGRAMMER-PAUL LIN(LEC 626-45 SOFTWARE
DEVELOPMENT SECTION)
DATE-SEPT 3, 1976
FUNCTION-CONVERT 2 WORDS READ FROM 7 TRACK TAPE
TO 3 WORDS(1 BYTE/WORD, RIGHT JUSTIFIED)

EXAMPLE:

FROM WORD 1:00000000 00000000
WORD 2:00222222 00000000
TO WORD 1:00000000 00000000
WORD 2:00000000 00002222
WORD 3:00000000 00000000

SOURCE=<CON79:A>
OBJECT=<CON79:R>

CALLING SEQUENCE:

CALL CON79(IA,IB)

WHERE IA IS A 2-WORD INPUT ARRAY READ FROM 7 TRACK TAPE

IB IS A 3-WORD OUTPUT ARRAY, 1 BYTE/WORD, RIGHT JUSTIFIED

ENT CON79
EXTD .CPYL, .FRET
NREL

CON79 2
JSR @CPYL
STA 3,SAVE
LDA 0,FTSTR,3
LDA 2,FTSTR+1,3

LIST LINES - 65

```

      MOV 0,3
      PROCESS 1ST OUTPUT BYTE
      LDA 0,0,3
      LDA 1,MASK1
      AND 1,0
      LDA 1,SHFT4
CON01  MOUZR 0,0
      INC 1,1,SZR
      JMP CON01
      STA 0,TEMP

      LDA 0,0,3
      LDA 1,MASKR
      AND 1,0
      LDA 1,SHFT6
CON02  MOUZR 0,0
      INC 1,1,SZR
      JMP CON02

      LDA 1,TEMP
      ADD 1,0
      STA 0,0,2

      PROCESS 2ND OUTPUT BYTE

      LDA 0,0,3
      LDA 1,MASK2
      AND 1,0
      LDA 1,SHFT4
CON03  MOUZR 0,0
      INC 1,1,SZR

```

```

JMP CON03
STA 0,TEMP

```

```

LDA 0,1,3
LDA 1,MASKR
AND 1,0
MOUS 0,0
MOUZR 0,0
MOUZR 0,0

```

```

LDA 1,TEMP
ADD 1,0
STA 0,1,2

```

PROCESS 3RD OUTPUT BYTE

```

LDA 0,1,3
LDA 1,MASKL
AND 1,0
STA 0,TEMP
LDA 0,1,3
LDA 1,MASK3
AND 1,0
MOUZR 0,0
MOUZR 0,0

```

```

LDA 1,TEMP
ADD 1,0
STA 0,2,2

```

```

LDA 3,SAVE
JSR 0,FRET

```

READY

LIST LINES - 65

MASK1 000060 ;GET BITS 10,11
MASK2 000017 ;GET BITS 12-15
MASK3 001400 ;GET BITS 6,7
MASK4 000377 ;GET BITS 8-15
MASK5 177400 ;GET BITS 0-7
SHIFT4 -4
SHIFT6 -6
SHUE 0
TEMP 0
END

READY

3.2.6 COMPONENT NO. 6 (RDLIN)

3.2.6.1 Linkage

Subroutine RDLIN is the driver (main) routine in overlay T2. RDLIN calls the user subroutines ISET, CON79, and FRAME, as well as various system subroutines which read the input tape and create the temporary data file TDATA. After execution, RDLIN calls in overlay T3.

3.2.6.2 Interface

Subroutine RDLIN communicates with its associate subroutines via the common parameter block ICONS.

3.2.6.3 Input

Subroutine RDLIN accepts input from the 7-track input data tape.

3.2.6.4 Output

RDLIN creates a temporary data file TDATA on the system disk.

3.2.6.5 Storage Requirements

Subroutine RDLIN requires 1054 words in core.


3.2.6.6 Description

Subroutine RDLIN reads the classified data tape, packs the classified data 16 pixels per word, and stores these data on a temporary disk file, TDATA.

3.2.6.7 Flowchart

3.2.6.8 Listing

(RDLIN)



ORIGINAL PAGE IS
OF POOR QUALITY

```

                                READY
DIMENSION IN (2), IB(3), IS(50), IA(4080)
COMMON /ICONS/ ID(14), OPTNS(16), IFLG1
DATA LNCNT, IEND /0,0/
NAME (1) = "T3"
NAME (2) = "/1"
NAME (3) = 0
IER = 0
CALL FOFPL ("TDATA", IER)
CALL FOPFL ("TDATA", 1, 1, IER)
50 KT = 1
   NIT = 0
   IPAR = ID(14)
   LINRC = 0
   ISTAT = 0
   NWDS = 0
   DO 60 K = 1, 50
   IS(K) = 0
60 CONTINUE
   IF (IEND - 1) 70, 390, 390
70 ICLS = OPTNS(6)
   N = 4080
80 CALL ROTAPE (NIT, IA, N, IPAR, NSMR, ISTAT)
   NOL = OPTNS(4) - OPTNS(3) + 1
   IF (NOL) 90, 90, 100
90 NOL = ID(6)
   GO TO 115
100 IF (NOL - ID(6)) 115, 115, 110
110 WRITE (10, 615) NOL, ID(6)
615 FORMAT (1X, " WANT", 15, " PIXELS PER LINE? WILL TRY", 15)
   NOL = ID(6)
   OPTNS(4) = 0
115 IF (ISTAT - 4) 160, 140, 120
120 IEND = IEND + 1

```

```

                                READY
IF (IEND - 1) 140, 125, 390
125 WRITE (10, 620) ISTAT, LNCNT
620 FORMAT (1X, " STATUS WORD =", I3, " TOTAL LINES DONE IS", I5)
140 WRITE (10, 620) ISTAT, LNCNT
160 IF (ID(8) - 1) 170, 400, 400
170 IADD = MOD (IFLG1, 10)
IF (IADD - 5) 200, 200, 180
180 IFLG1 = 5 - IADD
I00 = 0
GO TO 220
200 I00 = ID(4)
220 ISTAT = OPTNS(3)
L = OPTNS(5)
IP = ID(6) * (L - 1) + I00 + ISTAT
L = 0
240 IADD = 2 * (IP + (ID(6) * ID(5)) * LINRC)
I00 = MOD (IADD, 3)
ISTAT = 3 - I00
I00 = MOD (ISTAT, 3)
IADD = IADD/3
I = IADD + 1
IF (I00 - 2) 260, 250, 260
250 I = I - 1
260 IF (I - 4079) 270, 270, 350
270 IF (ID(8) - 1) 280, 410, 410
280 IN(1) = IA(I)
IN(2) = IA(I + 1)
CALL CON79 (IN, IB)
N = I00 + 1
DO 340 J = N, 3
NWDS = NWDS + 1
L = L + 1
IF (L - 16) 300, 300, 290

```

LIST LINES - 33

READY

```
290 L = 1
    KT = KT + 1
300 IF (ICLS - IB(J)) 340, 320, 340
320 CALL ISET (IS(KT), L)
340 CONTINUE
    IOO = 0
    I = I + 2
    IF (NMDS - NOL) 260, 260, 360
350 IFLG1 = MOD (IFLG1, 10)
    IF (IFLG1 - 5) 360, 360, 355
355 IFLG1 = 5 - IFLG1
360 LNCNT = LNCNT + 1
    LINRC = LINRC + 1
    ID (13) = KT
    IBYT = 2 * KT
    CALL FWTFL (1, IS, IBYT, IER)
    IF (LINRC - ID(9)) 362, 365, 365
362 KT = 1
    GO TO 240
365 ISTAT = OPTNS (2) - OPTNS(1) + 1.05
    IF (LNCNT - ISTAT) 380, 370, 370
370 IEND = 1
380 IF (LNCNT - 200) 50, 390, 390
390 CONTINUE
    CALL FRWFL (1, IER)
    CALL FCLFL (1, IER)
    IF (IER) 385, 395, 385
385 WRITE (10, 885) IER
885 FORMAT (1X, " ERROR SET AT", I5, " FROM WRITE, REWIND OR CLOSE")
    STOP
395 XSC=0.1
    YSC=0.1
    NLINES=OPTNS(2) - OPTNS(1) + 1.1
```

~~3-32~~

34

ORIGINAL PAGE IS
OF POOR QUALITY

```
NPX =OPTNS(4) - OPTNS(3) + 1.1  
XMAX=NPX  
YMAX=NLines  
CALL FRAME(XMAX,YMAX,XSC,YSC)  
CALL FRNOV (NAME, IER)  
PAUSE FRNOV IN READLINE FAILED.  
400 IEND = 1  
WRITE (10,900) ID(8)  
900 FORMAT (1X," IRREGULAR FORMAT INDICATED BY", I4)  
READ (11) I  
IF (I) 370, 370, 410  
410 ID(8) = -1  
IEND = 0  
GO TO 170  
END
```

READY

3.2.7 SOFTWARE COMPONENT NO. 7 (ISET)

3.2.7.1 Linkage

Subroutine ISET is called by RDLIN in overlay T2.

3.2.7.2 Interface

RDLIN communicates with subroutine ISET via two calling arguments.

3.2.7.3 Input

The argument IS(KL) is the KLth word in vector IS.

The argument L is the bit number in IS(KL) which needs to be set to 1.

3.2.7.4 Output

The argument IS(KL) is returned with the Lth bit set to 1.

3.2.7.5 Storage Requirements

Subroutine ISET requires 26 words in core.

3.2.7.6 Description

Subroutine ISET sets the appropriate bit in a 16-bit word to indicate a pixel belonging to the class being examined. These words are the packed data which RDLIN packs into the temporary data disk file TDATA.

3.2.7.7 Flowchart

3.2.7.8 Listing

(ISET)

START

SET THE
APPROPRIATE BITS
IN A 16-BIT
WORD TO INDICATE
WHICH PIXELS
BELONG TO THE
CLASS BEING EXAM.

RETURN

~~3-25~~

37

ORIGINAL PAGE IS
OF POOR QUALITY

LIST LINES - 60

READY

	TITL	ISCT
	ENT	ISCT
	EXTD	CPYL..FRET
	NREL	
	2	
ISCT	JSR	@.CPYL
	STA	3.SAVE
	LDA	0.@FTSTR,3
	STA	0.VALU
	NEG	0.1
	ADD	0.1
	MOVOR	1.1
	LDA	0.@FTSTR+1,3
	STA	0.@FTSTR+1,3
	STA	0,CONS
LOOP:	LDA	0,CONS
	DSZ	CONS
	JMP	RITS
	LDA	0,VALU
	ADD	0.1
	STA	1,VALU
	JMP	END
RITS	MOVOR	1.1
	JMP	LOOP
END	LDA	1,VALU
	STA	1.@FTSTR,3
	LDA	3.SAVE
	JSR	@.FRET
SAVE	0	
CONS	0	
VALU	0	
	END	

3.2.8 SOFTWARE COMPONENT NO. 8 (FRAME)

3.2.8.1 Linkage

Subroutine FRAME is called by RDLIN, and calls subroutine LINIT.

3.2.8.2 Interface

FRAME receives format and scaling information through four input parameters.

3.2.8.3 Input

Four calling arguments are input to subroutine FRAME reflecting format and scaling constraints.

3.2.8.4 Output

None

3.2.8.5 Storage Requirements

Subroutine FRAME requires 347 words in core.

3.2.8.6 Description

Subroutine FRAME computes the output frame size, generates four corner ticks for the plot file, and calls subroutine LINIT to write these ticks in the plot file.

3.2.8.7 Flowchart

3.2.8.8 Listing

(FRAME)

START

SET UP X,Y
ARRAY FOR
LOWER LEFT TICK

LIMIT
PLOT LOWER LEFT
TICK IN
DRAWING FILE

SET UP X,Y
ARRAY FOR LOW-
ER RIGHT TICK

LIMIT
PLOT LOWER
RIGHT TICK IN
DRAWING FILE

SET UP X,Y
ARRAY FOR
UPPER RIGHT TICK

LIMIT
PLOT UPPER
RIGHT TICK IN
DRAWING FILE

SET UP X,Y ARRAY
FOR UPPER
LEFT TICK

LIMIT
PLOT UPPER
LEFT TICK
IN DRAWING FILE

RETURN

~~3-38~~

40

```

                                READY
SUBROUTINE FRAME(XMAX,YMAX,XSC,YSC)
DIMENSION X(3),Y(3)
ARM=0.5
X(1)=0.0
Y(1)=ARM * YSC
X(2)=0.0
Y(2)=0.0
X(3)=ARM * XSC
Y(3)=0.0
CALL LINIT(X,Y,3,0)
X(1)=(XMAX-ARM) * XSC
Y(1)=0.0
X(2)=XMAX * XSC
Y(2)=0.0
X(3)=X(2)
Y(3)=ARM * YSC
CALL LINIT(X,Y,3,0)
X(1)=XMAX * XSC
X(2)=X(1)
Y(1)=(YMAX-ARM) * YSC
Y(2)=YMAX * YSC
X(3)=(XMAX-ARM) * XSC
Y(3)=Y(2)
CALL LINIT(X,Y,3,0)
X(1)=ARM * XSC
Y(1)=YMAX * YSC
Y(2)=Y(1)
X(2)=0.0
X(3)=0.0
Y(3)=(YMAX-ARM) * YSC
CALL LINIT(X,Y,3,0)
RETURN
END

```

3.2.9 SOFTWARE COMPONENT NO. 9 (LINIT)

3.2.9.1 Linkage

In overlay T2 subroutine LINIT is called by subroutine FRAME.
In overlay T3 subroutine LINIT is called by BDT3, ENDTST, CONALL, CLSTST, CONECT, and FINDAR.

3.2.9.2 Interface

Subroutine LINIT receives control information through the user common block ICONS, and through the System 100 common blocks BLK and MENU1.

3.2.9.3 Input

LINIT receives x,y plot arrays through its calling arguments.

3.2.9.4 Output

Subroutine LINIT transfers registered boundary plot string arrays to a System 100 drawing file.

3.2.9.5 Storage Requirements

Subroutine LINIT requires 313 words in core.

3.2.9.6 Description

LINIT accepts as input plot string arrays. Data registration is accomplished at this point by transforming the x,y coordinates of the plot arrays using either the eight coefficients input by the user or the default (no change) coefficients. The standard expression for the data transformation is:

$$X_t = (A_1X_0 + A_2Y_0 + A_3)/(1 + A_4Y_0 + A_5Y_0)$$

$$Y_t = (A_6X_0 + A_7Y_0 + A_8)/(1 + A_4X_0 + A_5Y_0)$$

where

A_1-A_9 are the eight coefficients

X_0, Y_0 = Initial or observed coordinates

X_t, Y_t = Transformed coordinates

After transformation, these registered plot string arrays are transferred to a standard System 100 drawing file.

3.2.9.7 Flowchart

3.2.9.8 Listing

(LINIT)

START

Perform 8 parameter transformation
using either
coefficients input
by user or
default
coefficients

Send Arrays to
Drawing File

Return

LIST LINES -

END

```

SUBROUTINE LINIT(ARX,ARY,N,ITYREADY
DIMENSION ARX(50),ARY(50)
COMMON /ICONS/ IZ(14),O(16),IFLG1
COMMON /BLK/X(30),Y(30),A(10),K(30),KP,ID(80)
COMMON /MENU1/KODE,MRFLG,SFACT,LNMOD,LNWID
EQUIVALENCE (X(1),X1),(Y(1),Y1),(K(11),K11),(K(12),K12)
EQUIVALENCE (K(14),K14),(K(15),K15),(A(1),A1),(A(2),A2)
C      DESIGNATE FILE NUMBER
      K4=1
      IF(ITYP.EQ.99) GO TO 20
      DO 1 I=1,N
      RX = ARX(I)
      RY = ARY(I)
      D = 1 + O(12) * RX + O(13) * RY
      ARX(I) = ( O(9)*RX + O(10)*RY + O(11) ) / D
1  ARY(I) = ( O(14)*RX + O(15)*RY + O(16) ) / D
C      PEN UP COMMAND
      X1=ARX(1)
      Y1=ARY(1)
      K11=1
      CALL RWCON(K4,2)
C      PEN DOWN COMMAND
      K11=6
      DO 10 I=2,N
      X1=ARX(I)
      Y1=ARY(I)
      CALL RWCON(K4,2)
10  CONTINUE
      GO TO 90
20  K11=31
C      WRITE END-OF-FILE COMMAND
      CALL PWCON(K4,2)
90  RETURN

```

3.2.10 SOFTWARE COMPONENT NO. 10 (BDT3)

3.2.10.1 Linkage

Subroutine BDT3 is the principal routine in overlay T3, and calls the following user subroutines: FINDAR, FILL, READAT, CONALL, ENDTST, CLSTST, and LINIT. In addition, subroutine BDT3 utilizes the following system subroutines for drawing file manipulation: FOPFL, FCLFL, FDLFL, and FCNOT.

3.2.10.2 Interface

Subroutine BDT3 receives control information through the common block ICONS. BDT3 communicates with its associate subroutines via the common blocks Z, ZZ, and MAXFIL.

3.2.10.3 Input

Pixel data is brought in, line by line, from the disk file TDATA by subroutine READAT and placed in common block ZZ for processing in BDT3.

3.2.10.4 Output

While overlay T3 is operating, BDT3 outputs a status message on the display device after each ten lines of requested data has been processed. In addition, BDT3 actuates the audible tone on the output device after processing is complete.

3.2.10.5 Storage Requirements

Subroutine BDT3 requires 9224 words in core.

3.2.10.6 Description



BDT3 is the routine which identifies, from the input pixel information, boundaries of a classified area or areas within a classified image. It processes the input data one line at a time,

identifying border pixels, and building plot string arrays which describe the limits of the classified areas. These plot strings are introduced into a standard system 100 drawing file through subroutine LINIT, which also accomplishes data transformation as specified by eight user-input coefficients, for registration onto any desired base. Ultimately, this drawing file is output on a magnetic tape which is used as input to the Gerber plotter, which creates the final registered boundary plot.


3.2.10.7 Flowchart

3.2.10.8 Listing

(BDT3)



346
48



3-AT
49

READY

```
COMMON /MAXFIL/ MXA
COMMON /Z/ NGRUP,ARRAYX(50,50),ARRAYY(50,50),ISIZE(50),ASIZE(50),
,ARX(50),ARY(50),LINE,YMAX,XSC,YSC,KAPPA
COMMON /ZZ/ IPIX(4,256),IPX(4,256),NPX,EPS
COMMON /ICONS/ ID(14),OPTNS(16),IFLG1
DIMENSION IAZ(256)
INTEGER ARRAYX,ARRAYY
MAXGRP=50
MXA = 0
EPS=OPTNS(7)
KAPPA=OPTNS(8)+0.1
IBYTE=2*ID(13)
XSC=0.1
YSC=0.1
KZ=1
NEPS=EPS + 1.0
NLINES=OPTNS(2) - OPTNS(1) + 1.1
NPX =OPTNS(4) - OPTNS(3) + 1.1
WRITE (10,3)NPX,NLINES
XMAX=NPX
YMAX=NLINES
C CALL FRAME(XMAX,YMAX,XSC,YSC)
NELEM=0
IF(NEPS.GT.4) WRITE(10,2) EPS
2 FORMAT(' EPSILON VALUE OF',F7.3,' EXCEEDS PRESENT PROGRAM CONSTRAI
NTS')
3 FORMAT(" NO. OF PIXELS PER LINE =",I4,/,/,
" NO. OF LINES TO BE PROCESSED =",I4,/,/)
CALL FOPFL("TDATA",2,0,IE)
IF(IE.EQ.0) GO TO 3
WRITE(10,599) IE
599 FORMAT(1X," IE=",I4)
PAUSE ERROR IN OPENING TDATA IN BDT3
```

READY

```
GO TO 990
5 CONTINUE
DO 7 I=1,NEPS
CALL READAT(IAZ,IBYTE)
DO 4 JZ=1,NPX
4 IPIX(I,JZ)=IAZ(JZ)
7 CONTINUE
DO 8 I=1,NEPS
DO 8 J=1,NPX
8 IPX(I,J)=IPIX(I,J)
LREAD=NEPS
CALL FILL
N=0
NGRUP=0
IFL=0
DO 10 IA=1,MAXGRP
ASIZE(IA)=0.
10 ISIZE(IA)=0.
C FIND UPPER BOUNDARIES ABOVE FIRST LINE ONLY
DO 100 IA=1,NPX
IF(IPX(1,IA)) 100,100,20
20 AX=IA-1
AY=0.
BX=IA
BY=0.
CALL FINDAR(AX,AY,BX,BY,0)
100 CONTINUE
LINE=0
C FIND LEFT AND RIGHT BOUNDARY PIXELS ON A LINE
C STORE LINE SEGMENTS IN APPROPRIATE ARRAYS
110 LINE=LINE+1
IT1=1
115 N1=IT1
```

READY

```
DO 200 IA=N1,NPX
  IF(IPX(1,IA)) 200,200,120
120 AX=IA-1
  AY=LINE-1
  BX=IA-1
  BY=LINE
  CALL FINDAR(AX,AY,BX,BY,0)
  DO 150 IB=IA,NPX
    IF(IB.EQ.NPX) GO TO 125
    IF(IPX(1,IB)) 130,130,150
125 IF(IPX(1,IB)) 130,130,126
126 AX=IB
  AY=LINE-1
  BX=IB
  BY=LINE
  GO TO 135
130 AX=IB-1
  AY=LINE-1
  BX=IB-1
  BY=LINE
135 CALL FINDAR(AX,AY,BX,BY,0)
  IF(IB.EQ.NPX) GO TO 210
  IT1=IB
  GO TO 115
150 CONTINUE
200 CONTINUE
210 CONTINUE
C  TEST FOR ARRAYS NOT CONTAINING ARRAYY(1,MAX)=LINE
  IF(MOD(LINE,KZ).NE.0) GO TO 290
  NNN=0
220 IPRB=0
  DO 223 IG=1,NGRUP
    IG1=ISIZE(IG)
```


READY

```
223 CONTINUE
    CALL CONALL(IPROB)
    CALL CLSTST
    IF(IPROB.EQ.1) GO TO 220
    CALL ENDTST
290 CONTINUE
C  FIND LOWER BOUNDARIES BELOW A LINE
    ISKP=0
    DO 300 IA=1,NPX
    IF(ISKP) 291,291,401
291 IF(IPX(1,IA).EQ.IPX(2,IA)) GO TO 300
    IF(IA.EQ.NPX) GO TO 299
    IPX1=IPX(1,IA)
    IPX2=IPX(2,IA)
    IPX3=IPX(1,IA+1)
    IPX4=IPX(2,IA+1)
    IF(IPX2.EQ.IPX4) GO TO 299
    IF(IPX1.EQ.IPX3)GO TO 299
    IF((IA-1).EQ.NPX) GO TO 402
    IPX5=IPX(1,IA+2)
    IPX6=IPX(2,IA+2)
    IF(IPX6.EQ.IPX4) GO TO 402
    IF(IPX3.EQ.IPX5) GO TO 402
    IF(IPX1.EQ.1.AND.EPS.GE.1.414) GO TO 410
    IF(IPX1.EQ.0.AND.EPS.LT.1.414) GO TO 410
    AX=IA
    AY=LINE
    BX=IA-1
    BY=LINE
    CALL FINDAR(AX,AY,BX,BY,2)
    AX=IA+1
    AY=LINE
    BX=IA+2
```

READY

```
BY=LINE
CALL FINDAR(AX,AY,BX,BY,2)
AX=IA
AY=LINE
BX=IA+1
BY=LINE
CALL FINDAR(AX,AY,BX,BY,4)
ISKP=2
GO TO 300
402 IF(IPX1.EQ.1.AND.EPS.LT.1.414) GO TO 415
    IF(IPX1.EQ.0.AND.EPS.GE.1.414) GO TO 415
410 AX=IA
    AY=LINE
    BX=IA+1
    BY=LINE
    CALL FINDAR(AX,AY,BX,BY,2)
    AX=IA-1
    AY=LINE
    BX=IA
    BY=LINE
    CALL FINDAR(AX,AY,BX,BY,2)
    ISKP=1
    GO TO 300
415 AX=IA
    AY=LINE
    BX=IA-1
    BY=LINE
    CALL FINDAR(AX,AY,BX,BY,2)
    AX=IA
    AY=LINE
    BX=IA+1
    BY=LINE
    CALL FINDAR(AX,AY,BX,BY,3)
```

~~352~~
54

READY

```
      ISKP=1
      GO TO 300
299  AX=IA-1
      AY=LINE
      BX=IA
      BY=LINE
      CALL FINDAR(AX,AY,BX,BY,1)
      GO TO 300
401  ISKP=ISKP-1
300  CONTINUE
      IF(MXA LT.20) GO TO 308
      WRITE(10,307)
307  FORMAT(1X," THIS CLASS TOO DENSE TO PROCESS A SECTOR THIS LARGE ",
     /,2X,"RETRY PROGRAM USING A SMALLER SPAN OF PIXELS/LINE")
      GO TO 990
308  CONTINUE
      IF(MOD(LINE,10).NE.0) GO TO 305
      WRITE(10,306) LINE
306  FORMAT(1X,I4," LINES PROCESSED")
305  CONTINUE
      IF(LINE.GE.NLINES) GO TO 999
C    SHIFT LINES UP ONE IN BOTH ARRAYS
      NEP=NEPS-1
      DO 310 I=1,NEP
      DO 310 J=1,NPX
        IPIX(I,J)=IPIX(I+1,J)
        IPX(I,J)= IPX(I+1,J)
310  CONTINUE
C    READ IN NEW LINE
      IF(LREAD.GE.NLINES) GO TO 500
      LREAD=LREAD+1
      CALL READAT(IAZ,IBYTE)
      DO 320 JZ=1,NPX
```

```

320 IPIX(NEPS,JZ)=IAZ(JZ)
GO TO 600
500 DO 501 J=1,NPX
501 IPIX(NEPS,J)=0
600 CONTINUE
DO 700 J=1,NPX
700 IPX(NEPS,J)=IPIX(NEPS,J)
CALL FILL WILL BE INSERTED HERE
CALL FILL
GO TO 110
999 NNN=1
1000 IPROB=0
CALL CONALL(IPROB)
CALL CLSTST
CALL ENDTST
DO 800 J=1,NGRUP
IZ=ISIZE(J)
IF(IZ) 800,800,750
750 IF(IPROB.EQ.1) GO TO 1000
GO TO 801
800 CONTINUE
801 CONTINUE
CALL LINIT(ARX,ARY,11,99)
990 CONTINUE
CALL FCLFL(2,IE)
CALL FOLFL("TDATA",IE)
CALL FCNOT("<7>")
CALL OURLY(1,IER) ; RETURN TO PROG1 OF SYSTEM 101
PAUSE OURLY ERROR-NO RETURN TO SYSTEM 101
END

```

READY

~~54~~
56

3.2.11 SOFTWARE COMPONENT NO. 11 (READAT)

3.2.11.1 Linkage

Subroutine READAT is called by subroutine BDT3, and calls subroutine IGET.

3.2.11.2 Interface

READAT transmits pixel information through the following two calling arguments:

IA - vector containing one line of classified pixel indicators, unpacked to one pixel per word.

IBYTE - number of bytes/line to be read from the temporary data file TDATA.

3.2.11.3 Input

Subroutine READAT reads in bit images of line data from the data disk file, TDATA.

3.2.11.4 Output

An error message may be displayed if a disk read error is encountered.

3.2.11.5 Storage Requirements

Subroutine READAT requires 125 words in core.

3.2.11.6 Description

Subroutine READAT reads in one line of packed pixel data from TDATA, unpacks the data into array IA using subroutine IGET, and transfers this line of data to subroutine BDT3.

3.2.11.7 Flowchart

3.2.11.8 Listing

```

SUBROUTINE READAT(IA,IBYTE)
DIMENSION IRAY(16),IA(256)
IWDS = IBYTE / 2
CALL FROFL(2,IRAY,IBYTE,IBYTR,IE)
IF(IE.EQ.0) GO TO 12
PAUSE  DISK READ ERROR IN SUBROUTINE READAT
12 CONTINUE
IPT=0
DO 50 I=1,IWDS
DO 40 J=1,16
L=J
IT=IRAY(I)
CALL IGET(IT,L)
IPT=IPT + 1
IA(IPT)=IT
40 CONTINUE
50 CONTINUE
RETURN
END

```

READY

3.2.12 SOFTWARE COMPONENT NO. 12 (IGET)

3.2.12.1 Linkage

Subroutine IGET is called exclusively by subroutine READAT.

3.2.12.2 Interface

Communication with READAT is accomplished through two calling arguments.

3.2.12.3 Input

Subroutine READAT requests the status of the Lth bit of word I from subroutine IGET.

3.2.12.4 Output

Subroutine IGET outputs the status of the Lth bit for READAT.

3.2.12.5 Storage Requirements

Subroutine IGET unpacks the bit data read from the disk data file TDATA into subroutine READAT.

3.2.12.6 Description


Subroutine IGET unpacks the bit data read from the disk data file TDATA into subroutine READAT.

3.2.12.7 Flowchart

3.2.12.8 Listing

3-55
60

(IGET)



~~3-60~~

61

READY

	TITL	IGET
	ENT	IGET
	EXTD	.CPYL, .FRET
	NREL	
	2	
IGET:	JSR	@.CPYL
	STA	3.RETN
	LDA	0,@FTSTR+1,3
	STA	0,CONS
	NEG	0,1
	ADD	0,1
	MOVOR	1,1
POOL:	DSZ	CONS
	JMP	STIR
	JMP	MSK
STIR:	MOVOR	1,1
	JMP	POOL
MSK:	LDA	0,@FTSTR,3
	STA	1,@FTSTR+1,3
	AND	0,1,SZR
	JMP	DOUT
	LDA	1,ZERO
	STA	1,@FTSTR,3
	JMP	BACK
DOUT:	LDA	1,ONE1
	STA	1,@FTSTR,3
BACK:	LDA	3.RETN
	JSR	@.FRET
PETN	0	
CONS	0	
ZERO	0	
ONE1	1	
	END	

3-61

022

3.2.13 SOFTWARE COMPONENT NO. 13 (FILL)

3.2.13.1 Linkage

Subroutine FILL is called exclusively by subroutine BDT3.

3.2.13.2 Interface

Communication of data between subroutines FILL and BDT3 is accomplished through the common block ZZ.

3.2.13.3 Input

The data block IPIX enters subroutine FILL via ZZ.

3.2.13.4 Output

The data block IPX exits subroutine FILL via ZZ.

3.2.13.5 Storage Requirements


Subroutine FILL requires 584 words of core.

3.2.13.6 Description

Subroutine FILL redefines appropriate pixels as classified to facilitate connectivity of "close" groups. The user defines the criteria for "closeness" via the input parameter Epsilon.


3.2.13.7 Flowchart

3.2.13.8 Listing



3-63

64



~~3-64~~
65

READY

```
SUBROUTINE FILL
COMMON /ZZ/ IPIX(4,256), IPX(4,256), NPX, EPS
N=EPS
L=1
  DO 100 IP=1, NPX
    IF( IPIX(1, IP).EQ.0 ) GO TO 100
    LFP=IP-N
    IF( LFP.LT.1 ) LFP=1
    IRP=IP+N
    IF( IRP.GT.NPX ) IRP=NPX
    IBR=L+N
    DO 20 J=L, IBR
      DO 10 I=LFP, IRP
        IF( J.EQ.L.AND.I.LE.IP ) GO TO 10
        IF( IPIX(J, I) ) 10, 10, 11
11      JPIX=(I-IP)**2 + (J-L)**2
        PIXDST=SQRT(FLOAT(JPIX))
        IF( PIXDST.GT.EPS ) GO TO 10
        IF( IABS(I-IP).EQ.IABS(J-L) ) GO TO 10
        IF( I-IP ) 12, 14, 13
12      IPLUS=I+1
        DO 15 II=IPLUS, IP
15      IPX(J, II)=1
        GO TO 14
13      IMIN=I-1
        DO 16 II =IP, IMIN
16      IPX(J, II)=1
14      IF( (J-L).LE.1 ) GO TO 10
        LPLUS=L+1
        DO 17 JJ=LPLUS, J
17      IPX(JJ, IP)=1
        GO TO 10
18      IF( I-IP ) 19, 14, 21
```

```

                                RETURN
                                END
19  IPLU=I+1
    IPM=IP-1
    IF((IPM-IPLU).LT.0) GO TO 10
    JJ=J
    DO 30 II=IPLU,IPM
    JJ=J-1
30  IPX(JJ,II)=1
    GO TO 10
21  IPPL=IP+1
    IM=I-1
    IF((IM-IPPL).LT.0) GO TO 10
    JJ=L
    DO 40 II=IPPL,IM
    JJ=JJ+1
40  IPX(JJ,II)=1
10  CONTINUE
20  CONTINUE
100 CONTINUE
    IF(N.LT.2) GO TO 300
    NPXX=NPX-N
    DO 200 IP=1,NPXX
    IF(IPIX(2,IP).EQ.0) GO TO 200
    IRB=IP+N
    IPP=IP+2
    DO 220 I=IPP,IRB
    IF(IPIX(2,I).EQ.0) GO TO 220
    IP1=IP+1
    IR1=I-1
    DO 240 J=IP1,IR1
240 IPX(2,J)=1
220 CONTINUE
200 CONTINUE
300 CONTINUE

```

3.2.14 SOFTWARE COMPONENT NO. 14 (FINDAR)

3.2.14.1 Linkage

Subroutine FINDAR is called by subroutine BDT3, and calls subroutines CONECT, AREAL, and LINIT.

3.2.14.2 Interface

Subroutine FINDAR receives control information via common blocks Z and MAXFIL (see Appendix A), and via five calling arguments.

3.2.14.3 Input

None

3.2.14.4 Output

None

3.2.14.5 Storage Requirements


Subroutine FINDAR requires 693 words in core.

3.2.14.6 Description

Subroutine FINDAR accepts as input a boundary line segment, finds the plot string array, if any, to which the segment connects, and adds it. If no such array exists, new arrays are formed initializing on this segment.

3.2.14.7 Flowchart

3.2.14.8 Listing



```

                                READY
SUBROUTINE FINDAR(XA,YA,XB,YB,ITYPE)
COMMON /MAXFIL/ MXA
COMMON /Z/ NGRUP,ARRAYX(50,50),ARRAYY(50,50),ISIZE(50),ASIZE(50),
      .ARX(50),ARY(50),LINE,YMAX,XSC,YSC,KAPPA
INTEGER ARRAYX,ARRAYY
MAXGRP=50
IPASS=0
IF(ITYPE-2) 9,9,210
9 IF(NGRUP) 200,200,10
10 DO 100 IA=1,NGRUP
    I1=ISIZE(IA)
    IF(I1-1) 100,100,11
11 DIF1=XA-ARRAYX(IA,I1)
    IF(ABS(DIF1).GT.0.01) GO TO 100
    DIF2=YA-ARRAYY(IA,I1)
    IF(ABS(DIF2).GT.0.01) GO TO 100
    IHOLD=IA
    IF(I1-1) 45,45,12
12 I1M=I1-1
    XO=ARRAYX(IA,I1M)
    YO=ARRAYY(IA,I1M)
    IF(ABS(XO-XA).GT.0.01) GO TO 25
    IF(ABS(XA-XB).GT.0.01) GO TO 25
    GO TO 46
25 IF(ABS(YO-YA).GT.0.01) GO TO 45
    IF(ABS(YA-YB).GT.0.01) GO TO 45
    GO TO 46
45 ISIZE(IA)=ISIZE(IA) + 1
    I1=ISIZE(IA)
46 ARRAYX(IA,I1)=XB
    ARRAYY(IA,I1)=YB
    IF(ITYPE-1) 902,902,900
100 CONTINUE

```

READY

```
      IF( IPASS ) 101,101,200
101  IPASS=1
      IF( ITYPE-1 ) 110,110,200
110  TEMP=XB
      XB=XA
      XA=TEMP
      TEMP=YB
      YB=YA
      YA=TEMP
      GO TO 10
200  IF( IPASS ) 210,210,201
201  TEMP=XA
      XA=XB
      XB=TEMP
      TEMP=YA
      YA=YB
      YB=TEMP
210  DO 300 IA=1,MAXGRP
      IF( ISIZE(IA)) 220,220,300
220  ARRAYX(IA,1)=XA
      ARRAYY(IA,1)=YA
      ARRAYX(IA,2)=XB
      ARRAYY(IA,2)=YB
      ISIZE(IA)=2
      IF( IA.GT.NGRUP ) NGRUP=IA
      IHOLD=IA
      GO TO 900
300  CONTINUE
      MXA = MXA + 1
      WRITE(10,5) LINE
5  FORMAT(20X,'ALL ARRAYS FILLED AT LINE',I4)
      GO TO 990
900  IF( ITYPE-3 ) 901,901,990
```

```

901 CALL CONECT(IHOLD)
902 DO 909 IA=1,NGRUP
    NU=ISIZE(IA)
    IF(NU.LT.49) GO TO 909
    DO 920 JK=1,NU
        ARX(JK)=ARRAYX(IA,JK) * XSC
920  ARY(JK)=(YMAX-ARRAYY(IA,JK)) * YSC
        CALL AREA1(IA,AREA)
        CALL LINIT(ARX,ARY,NU,0)
        ASIZE(IA)=ASIZE(IA)+AREA
        ARRAYX(IA,1)=ARRAYX(IA,NU)
        ARRAYY(IA,1)=ARRAYY(IA,NU)
        ISIZE(IA)=1
909  CONTINUE
990  CONTINUE
    RETURN
    END

```

READY

~~3-71~~
72

3.2.15 SOFTWARE COMPONENT NO. 15 (CONNECT)

3.2.15.1 Linkage

Subroutine CONNECT is called by subroutine FINDAR, and calls subroutines LINIT, AREAL, and JOIN.

3.2.15.2 Interface

Subroutine CONNECT receives control information through common block Z (see Appendix A).

3.2.15.3 Input

None

3.2.15.4 Output

None

3.2.15.5 Storage Requirements

Subroutine CONNECT requires 435 words in core.


3.2.15.6 Description

Subroutine CONNECT accepts as input a particular plot string array and forces immediate connection with the appropriate other plot string array.

3.2.15.7 Flowchart

3.2.15.8 Listing

(CONNECT)



ORIGINAL PAGE IS
OF POOR QUALITY

READY

```
SUBROUTINE CONECT(IH)
COMMON /Z/ NGRUP,ARRAYX(50,50),ARRAYY(50,50),ISIZE(50),ASIZE(50),
,ARX(50),ARY(50),LINE,YMAX,XSC,YSC,KAPPA
INTEGER ARRAYX,ARRAYY
IB=ISIZE(IH)
XA=ARRAYX(IH,IB)
YA=ARRAYY(IH,IB)
IF(NGRUP) 909,909,10
10 DO 100 I=1,NGRUP
  IF(I.EQ.IH) GO TO 100
  I1=ISIZE(I)
  IF(I1.LT.1) GO TO 100
  DIF1=XA-ARRAYX(I,I1)
  IF(ABS(DIF1).GT.0.01) GO TO 100
  DIF2=YA-ARRAYY(I,I1)
  IF(ABS(DIF2).GT.0.01) GO TO 100
  IH2=I
  GO TO 102
100 CONTINUE
  GO TO 909
102 IB2=ISIZE(IH2)
  IF(IB2-1) 909,200,900
200 J=IB+1
  DO 300 I=1,IB
    J=J-1
    ARX(I)=ARRAYX(IH,J)
300 ARY(I)=ARRAYY(IH,J)
    DO 400 I=1,IB
      ARRAYX(IH,I)=ARX(I)
400 ARRAYY(IH,I)=ARY(I)
    DO 500 I=1,IB
      ARX(I)=ARRAYX(IH,I) * XSC
500 ARY(I)=(YMAX-ARRAYY(IH,I)) * YSC
```

```
CALL LINIT(ARX,ARY,IB,0)
CALL AREA1(IH,AREA)
ASIZE(IH2)=ASIZE(IH2) + AREA
ARRAYX(IH2,1)=ARRAYX(IH,IB)
ARRAYY(IH2,1)=ARRAYY(IH,IB)
ISIZE(IH)=0
GO TO 909
900 CALL JOIN(IH,IB,IH2,IB2,3)
909 RETURN
END
```

READY

3.2.16 SOFTWARE COMPONENT NO. 16 (CONALL)

3.2.16.1 Linkage

Subroutine CONALL is called by subroutine BDT3, and calls subroutines JOIN, AREAL, and LINIT.

3.2.16.2 Interface

Subroutine CONALL receives control information through common block Z (see Appendix 1) and one calling argument.

3.2.16.3 Input

None

3.2.16.4 Output

None

3.2.16.5 Storage Requirements

Subroutine CONALL requires 513 words in core.


3.2.16.6 Description

Subroutine CONALL determines which plot string arrays should be linked or connected, and how they should be joined (ordering).


3.2.16.7 Flowchart

3.2.16.8 Listing

(CONALL)



3-27
78



ORIGINAL FILED
IN 100-100000000

READY

```
SUBROUTINE CONALL(IPROB)
COMMON /Z/ NGRUP,ARRAYX(50,50),ARRAYY(50,50),ISIZE(50),ASIZE(50)
,ARX(50),ARY(50),LINE,YMAX,XSC,YSC,KAPPA
INTEGER ARRAYX,ARRAYY
DO 200 J=1,NGRUP
  IS=ISIZE(J)
  IF(IS-1) 200,200,10
10 DO 100 I=1,NGRUP
  IF(I.EQ.J) GO TO 100
  IS2=ISIZE(I)
  IF(IS2-1) 100,100,20
20 IND=1
  XA=ARRAYX(J,1)
  YA=ARRAYY(J,1)
  XB=ARRAYX(I,1)
  YB=ARRAYY(I,1)
22 DIF1=XA-XB
  IF(ABS(DIF1).GT.0.01) GO TO 25
  DIF2=YA-YB
  IF(ABS(DIF2).GT.0.01) GO TO 25
  IPROB=1
  JA=J
  ISA=IS
  IA=I
  IS2A=IS2
  CALL JOIN(JA,ISA,IA,IS2A,IND)
  IS=ISIZE(JA)
  J=JA
  IF(IS.LT.24) GO TO 24
  DO 23 IJ=1,IS
  ARX(IJ)=ARRAYX(J,IJ) * XSC
23 ARY(IJ)=(YMAX-ARRAYY(J,IJ)) * YSC
  CALL LINIT(ARX,ARY,IS,0)
```

ORIGINAL PAGE IS
OF POOR QUALITY

```

CALL AREA1(J,AREA)
ASIZE(J)=ASIZE(J) + AREA
IF (ARRAYY(J,1).LT.LINE) GO TO 235
ASIZE(IA)=0
ARRAYX(IA,1)=ARRAYX(J,1)
ARRAYY(IA,1)=ARRAYY(J,1)
ISIZE(IA)=1
235 ISIZE(J)=1
    ARRAYX(J,1)=ARRAYX(J,IS)
    ARRAYY(J,1)=ARRAYY(J,IS)
24 GO TO 200
25 IND=IND+1
    GO TO (20,30,40,50,100),IND
30 XB=ARRAYX(I,IS2)
    YB=ARRAYY(I,IS2)
    GO TO 22
40 XA=ARRAYX(J,IS)
    YA=ARRAYY(J,IS)
    GO TO 22
50 XB=ARRAYX(I,1)
    YB=ARRAYY(I,1)
    GO TO 22
100 CONTINUE
200 CONTINUE
RETURN
END

```

READY

ORIGINAL PAGE IS
OF POOR QUALITY

3.2.17 SOFTWARE COMPONENT NO. 17 (JOIN)

3.2.17.1 Linkage

Subroutine JOIN is called by subroutines CONECT and CONALL.

3.2.17.2 Interface

Subroutine JOIN receives control information through common block 2 (see Appendix A).

3.2.17.3 Input

None

3.2.17.4 Output

None

3.2.17.5 Storage Requirements

Subroutine JOIN requires 358 words in core.



3.2.17.6 Description

Subroutine JOIN connects plot string arrays as determined by subroutines CONALL and CONECT. Arrays which are no longer needed, i.e., whose coordinates have been linked to another array, are flagged for reuse.

3.2.17.7 Flowchart

3.2.17.8 Listing

(JOIN)



~~3-82~~

83

READY

```
SUBROUTINE JOIN(J,IS,I,IS2,IND)
  DIMENSION ATX(50),ATY(50)
  COMMON /Z/ NGRUP,ARRAYX(50,50),ARRAYY(50,50),ISIZE(50),ASIZE(50)
  ,ARX(50),ARY(50),LINE,YMAX,XSC,YSC,KAPPA
  INTEGER ARRAYX,ARRAYY
  IF(IND.NE.2) GO TO 1
  IT=J
  J=I
  I=IT
  IT=IS
  IS=IS2
  IS2=IT
  1 GO TO (10,30,20,30),IND
10 ISM=IS+1
  DO 12 II=1,IS
    ISM=ISM-1
    ATX(ISM)=ARRAYX(J,II)
12 ATY(ISM)=ARRAYY(J,II)
    DO 14 II=1,IS
      ARRAYX(J,II)=ATX(II)
14 ARRAYY(J,II)=ATY(II)
    GO TO 30
20 ISM=IS2+1
  DO 22 II=1,IS2
    ISM=ISM-1
    ATX(ISM)=ARRAYX(I,II)
22 ATY(ISM)=ARRAYY(I,II)
    DO 24 II=1,IS2
      ARRAYX(I,II)=ATX(II)
24 ARRAYY(I,II)=ATY(II)
30 IJ=0
  NEWE=IS+IS2-1
  DO 30 II=IS,NEWE
```



```
IJ=IJ+1  
ARRAYX(J,IJ)=ARRAYX(I,IJ)  
50 ARRAYY(J,IJ)=ARRAYY(I,IJ)  
ISIZE(J)=NEW  
ISIZE(I)=0  
RETURN  
END
```

READY

3.2.18 SOFTWARE COMPONENT NO. 18 (CLSTST)

3.2.18.1 Linkage

Subroutine CLSTST is called by subroutine BDT3, and calls subroutines AREAL and LINIT.

3.2.18.2 Interface

Control information and data are communicated to subroutine CLSTST via common block Z (see Appendix A).

3.2.18.3 Input

None

3.2.18.4 Output

None

3.2.18.5 Storage Requirements


Subroutine CLSTST requires 324 words in core.

3.2.18.6 Description

Subroutine CLSTST accepts as input plot string arrays and determines whether these strings are complete, or "closed". Arrays which are complete are sent to subroutine AREAL for area computation, and upon returning, are plotted if the area is \geq Kappa, a user-supplied constant.

3.2.18.7 Flowchart

3.2.18.8 Listing



3-86
87

```

SUBROUTINE CLSTST
COMMON /Z/ NGRUP,ARRAYX(50,50),ARRAYY(50,50),ISIZE(50),ASIZE(50)
,ARX(50),ARY(50),LINE,YMAX,XSC,YSC,KAPPA
INTEGER ARRAYX,ARRAYY
IF(NGRUP) 999,999,10
10 DO 100 I=1,NGRUP
  A1=ASIZE(I)
  IF(ABS(A1).GT.0.1) GO TO 100
  I1=ISIZE(I)
  IF(I1.LT.2) GO TO 100
  DIF1=ARRAYX(I,1)-ARRAYX(I,I1)
  IF(ABS(DIF1).GT.0.01) GO TO 100
  DIF2=ARRAYY(I,1)-ARRAYY(I,I1)
  IF(ABS(DIF2).GT.0.01) GO TO 100
  CALL AREA1(I,AREA)
  IF(ABS(AREA).LT.KAPPA) GO TO 90
  DO 50 JK=1,I1
    ARX(JK)=ARRAYX(I,JK) * XSC
50  ARY(JK)=(YMAX-ARRAYY(I,JK)) * YSC
    CALL LINIT(ARX,ARY,I1,0)
    ASIZE(I)=ASIZE(I) + AREA
    LX=ARRAYX(I,1)
    LY=ARRAYY(I,1)
C    WRITE(10,60)LY,LX,ASIZE(I)
C 60  FORMAT(' AREA ',I3,' X ',I3,' )=',F8.2)
    ASIZE(I)=0
90  ISIZE(I)=0
100 CONTINUE
999 RETURN
END

```

READY

3.2.19 SOFTWARE COMPONENT NO. 19 (AREAL)

3.2.19.1 Linkage

Subroutine AREAL is called by subroutines CONECT, CONALL, FINDAR, CLSTST, and ENDTST.

3.2.19.2 Interface

Control information and data information are communicated by means of common block Z (see Appendix A).

3.2.19.3 Input

A plot string index is input to AREAL via a calling argument.

3.2.19.4 Output

An area value is output via a calling argument.

3.2.19.5 Storage Requirements

Subroutine AREAL requires 122 words in core.

3.2.19.6 Description

Subroutine AREAL accepts as input a plot string array, either partial or complete. AREAL computes the area or partial area in pixel units that this array represents.

3.2.19.7 Flowchart

3.2.19.8 Listing

(AREA1)

Start

Compute Area
of Designated
Plot Array

Return

~~3-89~~

90

```

SUBROUTINE AREA1(I, AREA)
COMMON /Z/ NGRUP, ARRAYX(50,50), ARRAYY(50,50), ISIZE(50), ASIZE(50)
, ARX(50), ARY(50), LINE, YMAX, XSC, YSC, KAPPA
INTEGER ARRAYX, ARRAYY
COMPUTE AREA USING ARRAYX(I, ALL), ARRAYY(I, ALL)
I1=ISIZE(I)
AREA=0.
DO 100 J=2, I1
DX=ARRAYX(I, J)-ARRAYX(I, J-1)
AREA=AREA + DX* ARRAYY(I, J)
100 CONTINUE
RETURN
END

```

READY

3.2.20 SOFTWARE COMPONENT NO. 20 (ENDTST)

3.2.20.1 Linkage

Subroutine ENDTST is called by subroutine BDT3, and calls subroutines AREAL and LINIT.

3.2.20.2 Interface

Subroutine ENDTST receives control information through common block Z (see Appendix A).

3.2.20.3 Input

None

3.2.20.4 Output

None

3.2.20.5 Storage Requirements


Subroutine ENDTST requires 723 words in core.

3.2.20.6 Description

Subroutine ENDTST handles, by segmentation, plotting and summation of area measurement for large plot strings which cannot be stored contiguously.

3.2.20.7 Flowchart

3.2.20.8 Listing



3-92
93

READY

```
SUBROUTINE ENDTST
DIMENSION LRX(50), LRY(50)
COMMON /2/ NGRUP, ARRAYX(50,50), ARRAYY(50,50), ISIZE(50), ASIZE(50)
, ARX(50), ARY(50), LINE, YMAX, XSC, YSC, KAPPA
INTEGER ARRAYX, ARRAYY
IF(NGRUP) 99,99,1
1 DO 10 I=1,NGRUP
  I1=ISIZE(I)
  IF(I1-1) 10,2,10
2 DO 9 J=1,NGRUP
  I2=ISIZE(J)
  IF(I2-1) 9,9,3
3 N=1
  AX1=ARRAYX(I,1)
  AY1=ARRAYY(I,1)
4 AX2=ARRAYX(J,N)
  AY2=ARRAYY(J,N)
  IF(ABS(AX1-AX2).GT.0.01) GO TO 5
  IF(ABS(AY1-AY2).GT.0.01) GO TO 5
  IF(N-1) 8,8,7
5 IF(N-I2) 6,9,6
6 N=I2
  GO TO 4
7 L=I2+1
  DO 71 LL=1,I2
  L=L-1
  LRX(LL)=ARRAYX(J,L)
71 LRY(LL)=ARRAYY(J,L)
  DO 72 LL=1,I2
  ARRAYX(J,LL)=LRX(LL)
72 ARRAYY(J,LL)=LRY(LL)
8 DO 88 L=1,I2
  ARX(L)=ARRAYX(J,L) * XSC
```

~~3-93~~
94

```

                                READY
88 ARY(L)=(YMAX-ARRAYY(J,L))* YSC
   CALL LINIT(ARX,ARY,12,0)
   CALL AREA1(J,AREA)
   ASIZE(I)=ASIZE(I) + AREA
   ISIZE(I)=1
   ARRAYX(I,1)=ARRAYX(J,12)
   ARRAYY(I,1)=ARRAYY(J,12)
   ISIZE(J)=0
   ASIZE(J)=0.
   GO TO 10
9  CONTINUE
10 CONTINUE
   DO 20 I=1,NGRUP
     I1=ISIZE(I)
     IF(I1-1) 20,11,20
11  DO 19 J=1,NGRUP
     IF(1-J) 12,19,12
12  I2=ISIZE(J)
     IF(I2-1) 19,13,19
13  AX1=ARRAYX(I,1)
     AY1=ARRAYY(I,1)
     AX2=ARRAYX(J,1)
     AY2=ARRAYY(J,1)
     IF(ABS(AX1-AX2).GT.0.01) GO TO 19
     IF(ABS(AY1-AY2).GT.0.01) GO TO 19
     LX=AX1
     LY=AY1
     AREA=ASIZE(I)-ASIZE(J)
C   WRITE(10,14)LY,LX,AREA
C 14 FORMAT(" AREA(",I3," , ",I3," )=",F8.2)
     ASIZE(I)=0.
     ASIZE(J)=0.
     ISIZE(I)=0

```

```

      ISIZE(J)=0
19  CONTINUE
20  CONTINUE
      DO 30 J=1,NGRUP
      J1=ISIZE(J)
      IF(J1-1)30,25,30
25  LX=ARRAYX(J,1)
      LY=ARRAYY(J,1)
      IF(LY.GE.LINE) GO TO 30
      ASIZE(J)=0
      ISIZE(J)=0
30  CONTINUE
99  RETURN
      END

```

READY

4. OPERATION

The users of this software system are researchers and analysts who need a method of comparing classification results to ground truth and an accurate means of production display of classification results. The input to this software system is a 7-track, 800 BPI universally formatted classification data tape directly or indirectly obtained from the GE Interactive Multispectral Image Analyst System (IMAGE 100), the Earth Resources Interactive Processing System (ERIPS), and the UNIVAC 1100 Software (EOD-LARSYS). If any of the above-mentioned systems does not support 7-track, 800 BPI output tape, the user may use the conversion capability available in Bldg. 12 to meet this requirement.

4.1 USER DOCUMENTATION

There is no formal user's document required in this phase implementation; the function of such a document is satisfied by the Technical Memorandum entitled "Software Specifications for Automated Thematic Plotting of Classified Digital Data", April 1976 (LEC 8289).

4.2 OPERATION DOCUMENTATION

N/A




Figure 1: Functional Diagram of Phase 1 Implementation of the Software System

**STARTING
OCTAL
NUMBER**


CORE MAP (32K)

0	Page 0 and Constants
440	1. Bendix System 100 labeled common 2. External references for Bendix System 100 in-core routines and plotter routines
3330	Fortran initialization routine - 1st routine executed by each overlay
4007	Fortran run-time linkage
4200	Fortran libraries
13651	Part 1 of Bendix System 100 subroutines
14234	Menu
16644	Part 2 of Bendix System 100 subroutines
30641	User's overlay
64000	Run time stack for main program
70704	1. Monitor 2. System loader 3. Paper tape loader 4. Key-in loader


} 13,919₁₀

Figure 2: Bendix System 100 Core Utilization Map

4-5
99




4-4/110
Figure 3: User's Procedure



4-8
101

Figure 3: User's Procedure (continued)



ORIGINAL PAGE IS
OF POOR QUALITY

FIGURE 4. The Functional Block Diagram
of BDT3

4/6/02

APPENDIX A
BDARPI COMMON TABLE

BDARP1 COMMON TABLE

No.	Title	Common Block	Initial Value	Initialized by	Referenced by	Modified by
1.	Header Record constants	ICONS	INPUT	REAH	REAH INITN RDLIN	REAH INITN
2.	Tape File Number	ICONS	INPUT	INPBD	REAH, INITN	--
3.	Tape Parity	ICONS	INPUT	INPBD	REAH, INITN	--
4.	Channel No.	ICONS	INPUT	INPBD	REAH, INITN	--
5.	Class Value	ICONS	INPUT	INPBD	RDLIN	--
6.	Starting/Ending Line	ICONS	INPUT	INPBD	RDLIN, BDT3	--
7.	Starting/Ending Pixel	ICONS	INPUT	INPBD	RDLIN, BDT3	--
8.	Epsilon Value	ICONS, ZZ	INPUT	INPBD	BDT3, FILL	--
9.	Kappa Value	ICONS, Z	INPUT	INPBD	CLSTST	--
10.	8 Registration coefficients	ICONS	INPUT	INPBD	LINIT	--
11.	Index on FINDAR failures due to all plot arrays being filled	MAXFIL	0	BDT3	BDT3, FINDAR	FINDAR
12.	No. of plot arrays in use	Z	0	BDT3	FINDAR	FINDAR
13.	X and Y arrays of current boundary plot strings	Z	0	FINDAR	*	*

BDARP1 COMMON TABLE (cont)

No.	Title	Common Block	Initial Value	Initialized by	Referenced by	Modified by
14.	Vector de- scribing length of each boundary string	Z	0	FINDAR	*	*
15.	Vector de- scribing area of each boundary string	Z	0	FINDAR	*	*, AREAL
16.	X and Y array of plot string in drawing file format	Z	0	*	*	*
17.	Present line number	Z	1	BDT3	BDT3, FILL	BDT3
18.	Pixel scaling factors, X&Y	Z	0.1, 0.1	BDT3	*	--
19.	Block of "pixel" data, unchanged	ZZ	INPUT	BDT3	BDT, FILL	--
20.	Block of "pixel" data after fill	ZZ	COMPUTED	FILL	BDT3, FILL	FILL
21.	No. of pixels/line	ZZ	COMPUTED	BDT3	BDT3, FILL	--

* denotes most of the following: BDT3, ENDTST, CLSTST, CONECT, CONALL, JOIN, and FINDAR.

105